Text Wizard™

COMMAND

REFERENCE

CARD



9421 Winnetka Ave. Chatsworth, CA 91311

Text Wizard

Editing Commands

Feature

Command Kevs

Upper Case Text SHIFT + CAPS/LOWR Lower Case Text

CAPS/LOWR

Inverse Character Remarks

Atari Logo

Moving the Cursor

Cursor UP Cursor DOWN Cursor LEFT Cursor RIGHT Page DOWN Page UP Top of Page

CTRL + Up Arrow CTRL + Down Arrow

CTRL + Left Arrow CTRL + Right Arrow OPTION + Down Arrow OPTION + UP Arrow

> SHIFT + CLEAR CTRL + CLEAR

OPTION + "T"

Bottom of Page TABBING the Cursor

OPTION + "B" TAB

INSERT Text

Character Insert Line Insert

CTRL + INSERT SHIFT + INSERT

Delete Text

Delete Character Left Delete Character Right Delete Line

Delete/Back S CTRL + Delete

Delete BLOCK

SHIFT + Delete START + SELECT + OPTION + "E"

MOVE Text

Set Start of Phrase Set End of Phrase Move Phrase

START + "M"

SELECT + "M" OPTION + "M"

Text Wizard

Feature Command Keys DUPLICATE Text

Set Start of Phrase START + "D"
Set End of Phrase SELECT + "D"
Duplicate Phrase OPTION + "D"

SEARCHING for Text

Define Search Phrase START + "S"
Search for Phrase SELECT + "S"

REPLACING Text

Define Replace Phrase START + "R" Replace Phrase SELECT + "R"

Printing Commands

Set LEFT Margin CTRL + "L"(nnn) Set RIGHT Margin CTRL + "R"(nnn) Set TOP Margin CTRL+ "I"(nn) CTRL + "D"(nnn) Set BOTTOM Margin Set Length of Form CTRL + "Y"(nnn) Set Line Spacing CTRL + "A"(n)CTRL + "S"(nnn) Character Spacing Second LEFT Margin CTRL + "M"(nn) Second RIGHT Margin CTRL + "N"(nnn)

Special Printing Features

CENTER Text CTRL + "C"

Block Text Right CTRL/C + CTRL/C

Proportional Print STANDARD

Condensed Print CTRL + "T"

Elongated Print CTRL + "E"

Subscripted Text CTRL + "F"

& CTRL + "B"

Text Wizard

Special Printing Features

<u>Feature</u>	Command Keys
Superscripted Text	CTRL + "B"
•	& CTRL + "F"
Underline Text	CTRL + "U"
Indent Text	Re-Set Margin
Justify Right	CTRL + "J"(1)
Un-Justify Right	CTRL + "J"(0)
Define HEADER	CTRL + "H"(phrase)
Define FOOTER	CTRL + "G"(phrase)
Set Page Number	CTRL + "Q"(nn)
Page Numbering	@ symbol
Eject Page	CTRL + "P"
WAIT at end of page	CTRL + "W"
CHAIN Files	CTRL + "V"(D:(nn))

Disk Commands

LOAD File	OPTION + "L"
SAVE File	OPTION + "S"
PRINT File	OPTION + "P"
DELETE File	OPTION + Delete
DISK Directory	OPTION + 1/2